## **Configuring NIC Teaming for Virtual Machines with Hyper-V 3.0**

The debut of Hyper-V 3.0 running on Windows Server 2012 featured several useful new networking features for administrators. One of the new additions is the ability to configure NIC teaming for Virtual Machines.

NIC Teaming, originally designed for the Windows Server 2012 host operating system, can now also be used for Hyper-V virtual machines running on Hyper-V 2012 and later operating systems. In the earlier versions of Hyper-V (version 1.0 and version 2.0), it was not possible to



configure NIC teaming for virtual machines.

Starting with Hyper-V version 3.0 on Windows Server 2012, you can easily configure NIC Teaming for virtual machines. Before you can configure NIC Teaming for virtual machines, ensure the following requirements are in place:

- Hyper-V Host is running Windows Server 2012 or later. Since the NIC Teaming feature was introduced in Windows Server 2012, the host must be running this version of the operating system.
- Similarly, virtual machines must be running the Windows Server 2012 (or later) operating system.
- There are at least two or more virtual network adapters available in the virtual machine and they are connected to different external virtual Hyper-V switches.
- You must create external virtual switches on the Hyper-V host. Each virtual NIC that is going to be part of the teaming must be connected to these external virtual switches. If you do not do so, you will see a "Faulted: The Virtual Switch lacks external connectivity" error message when configuring the NIC teaming inside the virtual machine. This indicates that Virtual Machine Teaming is not supported if virtual network adapters are connected to either private or internal virtual switches.
- Virtual network adapters must be configured to be available for the teaming. To do so, go to "Advanced Networking Settings" in the network configuration for the virtual machine and check "Enable this network adapter to be part of a team in the guest operating system" as shown in the screenshot below:



• By default, virtual machines are not configured to work with a teamed adapter. You must allow Virtual Machines to be configured with the NIC Teaming by executing the below PowerShell command:

Get-VM <VMName> | Set-VMNetworkAdapter -AllowTeaming On

What You Need to Know About Office 365 & Windows 10 Register Now

Once the "AllowTeaming" flag is set to **ON** for the virtual machine that is going to be used for the NIC Teaming, configure the NIC teaming in the virtual machine. It is as simple as configuring NIC Teaming on the Hyper-V Host. All you need to do is follow a simple set of steps of binding two or more virtual Network Adapters to a team:

1. Open Server Manager in the virtual machine, click on the Local Server in the left panel, and then click on "**Configure NIC Teaming**" as shown in the screenshot below:

<u>6</u>		Server Manager
Server Ma	anager • Hyper-V	
Dashboard     Local Server     All Server	SERVERS All servers   1 total	• ® • ®
AD DS	Server Name IPv4 Address	Manageability Last U
File and Storage Services      P     Hyper-V	HV-2012A 169.254.11.245,192.168	S6.1 Online Buforeare counter out studied 4020     Add Roles and Features     Shut Down Local Server
		Computer Management Remote Desktop Connection
	[[	Windows PowerShell Configure NIC Teaming Configure Windows Automatic Feedback
		Hyper-V Manager
	All events   0 total	Manage As Start Performance Counters Refresh
		Сору

2. In the NIC Teaming configuration page, click on "**TASKS**" and then click on "**New Team**" as shown in the below screenshot:

Name	Status	Server Type	Teams		
HV-2012A.devlab	.com 🕤 Online	Physical	0		
TEAMS			ADAPTERS AND INT	ERFACES	
TEAMS All Teams   0 total		TASKS V	ADAPTERS AND INT	ERFACES	TASKS 💌
TEAMS All Teams   0 total Team Status	Teaming I	TASKS  Vew Team Delete	ADAPTERS AND INT	ERFACES	TASKS 👻
FEAMS All Teams   0 total Team Status 1	Teaming I	TASKS  Vew Team Delete Properties	ADAPTERS AND INT Network Adapters Tear Adapter	ERFACES m Interfaces	TASKS 👻 State Rea
TEAMS All Teams   0 total Team Status	Teaming t	TASKS  Vew Team Delete Properties	ADAPTERS AND INT Network Adapters Tear Adapter Available to be a	ERFACES m Interfaces Speed added to a tea	TASKS 💌 State Rea
TEAMS All Teams   0 total Team Status 1	Teaming I	TASKS  Vew Team Delete Properties	ADAPTERS AND INT Network Adapters Tear Adapter Available to be a vEthernet (External)	m Interfaces Speed added to a tea 10 Gbps	TASKS  TASKS TASKS TASKS TASKS TASKS TASKS TASKS

3. In the "**New Team**" configuration page, specify the team name and select the network adapter that you want to include in the NIC Teaming. The new name we have specified in this example is "Hyper-VTeaming" as shown in the following screenshot:

	NIC Teami	ng			
New team Team name: Hyper-VTeaming					
Member adapters:	•		_	-	_
In Team Adapter	1	Speed S	State	Reason	
VEthernet (Extern	al) 1	10 Gbps			
VEthernet (New V	'irtual Switch)	10 Gbps			
<ul> <li>Additional properties</li> </ul>					
Teaming mode:	Switch Independ	dent		-	
Load balancing mode:	Address Hash			•	
Standby adapter:	None (all adapte	ers Active)		•	
Primary team interface:	Hyper-VTeaming	: Default V	<u>LAN</u>		
			(	OK Cance	

4. Under "Additional properties," you can configure the options such as Teaming Mode, Load Balancing mode and Standby adapter. Teaming Mode allows you to choose one of three teaming modes available — switch independent, static mapping, and LCAP. Virtual machine teaming can only run in the Switch Independent Mode and you also need to make sure to select "Address Hash" mode under the Load balancing mode or else teaming will not work.

**Note:** You can always modify the teaming options at a later stage or delete the teaming by going to the "Properties" page as shown in the screenshot below:

- Advertisement -

lame	Status	Server Tune	Teams			
N 2012A de de la		Dispisal	1			
		, ny sittai	•			
EAMS			ADAPTERS AND	INTERFAC	ES	
EAMS	I	TASKS 🔻	ADAPTERS AND	INTERFAC	ES TASKS	•
'EAMS Il Teams   1 total Team	I Status N	TASKS 💌 New Team	ADAPTERS AND	INTERFAC	ES TASKS	•
EAMS Il Teams   1 total Team	Status D	TASKS 🔻	ADAPTERS AND Network Adapters	INTERFAC	ES TASKS aces	•
EAMS II Teams   1 total Team	Status g • OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter	INTERFAC	ES TASKS aces Speed Stat	▼ te
EAMS II Teams   1 total Team Hyper-VTeaming	Status g • OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter	INTERFAC	ES TASKS acces Speed Stat	▼ te
EAMS II Teams   1 total Team	Status g ① OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter Alapter Hyper-VTea vEthernet (External)	INTERFAC	ES TASKS acces Speed Stat	• te Active
EAMS II Teams   1 total Team	Status g ① OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter Hyper-VTea vEthernet (External)	INTERFAC	ES TASKS acces Speed Stat	• te Active
EAMS II Teams   1 total Team	Status g • OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter Hyper-VTea vEthernet (External) vEthernet (New Virt	INTERFAC	ES TASKS aces Speed Stat 10 Gbps ① A 10 Gbps ① A	• te Active Active
EAMS   Teams   1 total Feam	Status g • OK p	TASKS  Vew Team Delete Properties	ADAPTERS AND Network Adapters Adapter Hyper-VTea vEthernet (External) vEthernet (New Virt	INTERFAC	ES TASKS sees Speed Stat	te Acti
AMS Teams   1 total am	Status g • OK p	TASKS     ▼       New Team     Delete       Properties	ADAPTERS AND Network Adapters Adapter Hyper-VTea vEthernet (External) vEthernet (New Virt	INTERFAC	ES TASKS aces Speed Stat 10 Gbps () / 10 Gbps () /	• te Active Active

Click on OK once you are done configuring the different options

The newly created teamed adapter will be available in the "Network Connections" page in the Control Panel as shown in screenshot below.



**Note:** At this point, since the teamed network adapter will be used by the network services running on the virtual machine, you need to configure the adapter with required TCP/IP configuration information, including the IP address, subnet masks, DNS Servers and so on.