
## **Managing Trust Relations**


## Managing Trust Relationships

- Open the Active Directory Domains And Trusts administrative tool by clicking Start >
  Administrative Tools > Active Directory Domains And Trusts.
- 2. Right-click the name of a domain and select Properties.
- To create a new trust relationship, click the New Trust button on the Trusts tab. The New Trust Wizard appears. Click Next to proceed with the wizard.
- On the Trust Name page, you are prompted for the name of the domain with which the trust should be created. Enter the name of the domain and click Next.




Note (you will be typing the name of the other domain not yours)


7. On the Trust Type page, you would normally choose the Trust With A Windows Domain option if you know that the other domain uses a Windows domain controller. In order to continue with this exercise (without requiring access to another domain), it is important to choose the Realm Trust option. This selection allows you to walk through the process of creating a trust relationship without needing an untrusted domain in the Active Directory environment. Click Next when you are done.




On the Transitivity Of Trust page, you choose whether the trust is transitive or intransitive. Choose the Nontransitive option and click Next to continue.




9. On the Direction Of Trust page, you select the direction of the trust. If you want both domains to trust each other, you select the two-way option. Otherwise you select either One-Way: Incoming or One-Way: Outgoing, depending on where the affected users are located. For the sake of this exercise, choose One-Way: Incoming and then click Next.



10. On the Trust Password page, you need to specify a password that should be used to administer the trust. Type P@ssw0rd and confirm it. Note that if there is an existing trust relationship between the domains, the passwords must match. Click Next to continue.



11. Now you see the Trust Selections Complete page that recaps the selections you have made. Because this is an exercise, you don't actually want to establish this trust. Click Cancel to cancel the wizard without saving the changes.



12. Exit the trust properties for the domain by clicking Cancel.

## To Enable Selective Authentication

- 1. In the console tree, right-click the name of a domain and select Properties.
- Select the Trusts tab. Under either Domains Trusted By This Domain (Outgoing Trusts)
  or Domains That Trust This Domain (Incoming Trusts), click the forest trust that you want
  to administer, and then click Properties.
- 3. On the Authentication tab, click Selective Authentication, and then click OK.